

minit

Installation guide

3.0 Enterprise Edition

Server

Introduction

This guide is intended for administrators of Minit v3 - Minit v3 Enterprise Edition Server, looking for a step-by-step guide to getting Minit application installed, setup and configured on their servers.

If you're looking to install Minit v3 - Enterprise Edition - Client on local machines, please follow the [Minit v3 Enterprise - Client Install Guide](#) instead. If you're looking to install Minit v3 Standalone Edition, please follow the instructions in [Minit v3 - Business Edition - Install Guide](#).

Table of content



Installation

01.1

Prerequisites


Recommended hardware and standard software configuration for Minit v3 – Enterprise Edition - Server.

CPU	4 cores
RAM	8 GB
HDD	SSD hard drive
Operating System	Windows Server 2012 R2/2016
Other standard software	.NET 4.7.1 Available Microsoft SQL Server 2014 (min. Express Edition)
Screen resolution	Minimum - 1280x768 Recommended - 1920x1080
Open ports	1719
User Accounts	User used for installation – Administrator privileges on the server User used for running the service – Create/Alter DB and DDL at the SQL Server

To install Minit v3 please, download the installation package and save it to your hard drive.


To start the installation, run the downloaded installation package minitSetup.exe and follow the steps below.

01.2 Installation



Choose the New Minit installation option.


01.3 Installation



Please accept the end user license agreement.

01.4


Installation



You can change the default Minit installation location if necessary.

The Shortcut Server option will install the Minit Light Client and create a shortcut on the server, under the currently logged-in user to be used for server administration.


01.5 Installation



Minit will keep you informed on the installation progress.

01.6

Installation




Congratulations! You have successfully installed Minit.

If any issues occur during the installation, Minit will automatically create log files. Please save these files and include them when contacting Minit Support at support@minit.io.

Configuration

02.1 Configuration



When you run the application for the first time, a configuration wizard will guide you through the application environment setup. In the case of server installation, the Minit client is used to configure the server environment.

Choose your preferred application user interface language.

02.2 Configuration

Starting the server


Please, enter password for provided user account. The credentials will be used for running Minit windows service.

Username

Password

Click Next to start the installation and startup of the server service for initial configuration.
Administrator privileges are required to successfully run it.
The wizard will prompt you for privileges when you click Next.

[PREVIOUS STEP](#) [NEXT STEP >](#)

A screenshot of the 'Server start' step of the Minit configuration wizard. The background is a gradient from red at the top to yellow at the bottom. At the top left is a circular progress bar with numbers 1 through 5. Step 1 is highlighted with a blue circle. In the center is a white cylinder icon with the text 'Server start'. At the bottom right is the 'minit' logo. A close button is in the top right corner of the window frame.

Enter the credentials of the user that will run the Minit server service.

Administrator privileges are necessary to run the configuration. You might be asked to enter the password when clicking **NEXT STEP** button.

02.3 Configuration

Database connection

The Minit database is used to store the Minit operational data.

SQL Server You can define your own connection to an existing SQL server.

[PREVIOUS STEP](#) [NEXT STEP >](#)



A database server is needed to store the operation data for Minit server.

The data from event logs are not stored in the database, so the size of the database will be small, and SQL Server Express Edition is sufficient in most cases.

02.4 Configuration

Database connection

The Minit database is used to store the Minit operational data.

PARAMETERS CONNECTION STRING

Server name: Database name:

Authentication:


[< PREVIOUS STEP](#) [NEXT STEP >](#)



A vertical step indicator on the right side of the configuration screen shows five numbered steps. Step 2 is highlighted with a red circle around the number 2. To the left of the steps is a large graphic of three stacked cylinders representing a database, with the word "Database" written below it. At the bottom of the graphic is the "minit" logo.


Provide SQL Server connection parameters or the complete connection string.

02.5 Configuration



Minit configuration wizard will start creating the Minit database.

02.6 Configuration



If a database with identical name exists (e.g. you uninstalled with Keep data and settings option checked), you have the possibility to:

USE

Connect to existing database


DELETE

Drop the database and create a new one

CANCEL

Cancel the database creation and change the settings, e.g. database name

02.7 Configuration




The screenshot shows the second step of a four-step wizard titled "Data storage location". The title bar indicates "Step 2 of 4". The main content area displays the text "Minit is storing process mining data at your file system." Below this, a "Data storage location:" label is followed by a text input field containing the path "C:\Users\minitadmin\Documents\Minit". A note "(please confirm the default location or change if necessary)" is shown below the input field. At the bottom of the screen are two buttons: "PREVIOUS STEP" and "NEXT STEP".

Once the database is created, provide a location of the data storage.

Data storage is an essential location and is used to store the data for process mining.

Please ensure that the location has enough free space, you have sufficient access rights to the location, it is not under centralized windows profile management and it is located on a fast storage device, such as SSD disc.

02.8 Configuration



If the data storage location exists and is not empty (e.g. you uninstalled with Keep data and settings option checked), you have the possibility to:

USE

Use the data storage with the data provided


CLEANUP

Erase the files in the location

CANCEL


Cancel the operation and change the location

02.9 Configuration



If the location is not found, you can create it (**YES**) or choose **NO** to change it.

02.10 Configuration



To activate the license online, please enter the license number provided with the installation package download link and click **ACTIVATE** button (if no internet connection is available, an offline activation procedure will start automatically – please follow the instructions).

If you do not have a license number, please contact Minit Support at support@minit.io or your local Minit partner.

You can click **NEXT STEP** button to proceed with the configuration and activate license later.

02.11

Configuration

Congratulations!


You have successfully set all configuration parameters. To apply the configuration, click the Apply and Mine! button.

Create a Demo project with pre-imported processes

Please don't forget to send us your feedback to feedback@minit.io

[PREVIOUS STEP](#)

[APPLY AND MINE!](#)



Congratulations! You have successfully configured Minit.

In the last step, you can choose, whether Minit should automatically create a demo project with two tutorial pre-imported processes. (This operation is available only if you have an activated license.)

Uninstallation



03.1


Uninstallation



To uninstall Minit, use the Add or Remove Programs feature in Windows Settings to locate Minit application and click the uninstall option.

03.2


Uninstallation



Choose the Remove Minit installation option.


03.3

Uninstallation




Let the **KEEP DATA AND SETTINGS** option checked to keep the Minit database and data storage for further use. Otherwise, the database will be deleted and data storage location cleaned.

03.4 Uninstallation



Minit will inform you of the uninstallation progress.

03.5 Uninstallation



Congratulations! You have successfully uninstalled Minit.

If any issues occur during the uninstallation, Minit will automatically create log files. Please save these files and include them when contacting Minit Support at support@minit.io.

